

Wialon IPS v.1.1 Communication protocol

IPS communication protocol was developed by Gurtam for personal and vehicle GPS/GLONASS trackers, which send data to satellite monitoring system server over TCP or UDP.

Incoming data (TCP)

All data is sent and received in plain text format over TCP protocol and has the following format:

#TP#msg\r\n

#	Start byte	
TP	Type of packet, all possible types are listed in table 1	
#	Separator	
msg	Message	
\r\n	End of message, <cr><lf> symbols (0D0A in HEX)</lf></cr>	





Packet types

Type	Description Sender	
L	Login Tracker	
AL	Answer to login	Server
D	Data packet	Tracker
AD	Answer to data packet	Server
P	Ping(heartbeat) packet	Tracker
AP	Answer to ping (heartbeat packet) Server	
SD	Short data packet Tracker	
ASD	Answer to short data packet Server	
В	Blackbox packet Tracker	
AB	Answer to blackbox packet	Server
M	Message to driver	Tracker/Server
AM	Reply to message from driver Server	
I	Packet with photo Tracker	
AI	Reply to packet with photo Server	
US	Packet with new firmware Server	
UC	Packet with configuration file Server	





Login packet

#L#imei;password\r\n

imei	Controller unique ID, IMEI, or serial number	
• •	Separator	
password	Password for access to device, if no password, then NA is sent	

Server sends answer to login packet, AL:

"1" – authorization successful

"0" – connection rejected by server

"01" – error checking password

Example:

 $\#AL\#1\r\n$

 $\#AL\#0\r\n$

Short data packet

#SD#date;time;lat1;lat2;lon1;lon2;speed;course;height;sats\r\n

date	Date in UTC format, DDMMYY, if no data, NA is sent	
time	Time in UTC format, HHMMSS, if no data, NA is sent	
lat1;lat2	Latitude (5544.6025;N), if no data, NA;NA is sent	
lon1;lon2	Longitude (5544.6025;N), if no data, NA;NA is sent	
speed	Speed, integer, km/h, if no data, NA is sent	
course	Course, integer, degrees, if no data, NA is sent	
height	Height, , integer, m, if no data, NA is sent	
sats	Number of satellites, integer, if no data, NA is sent	

If date and time fields is **NA**, server will set current time for packet.

Server sends ASD packet as an answer to SD packet:

"-1" – packet structure error

"0" – incorrect time

"1" - packet successfully registered

"10" – error getting coordinates

"11" – error getting height, speed or course

"12" – error getting amount of satellites

Example:

 $\#ASD\#1\r\n$

 $\#ASD\#0\r\n$





 $\#ASD\#10\r\n$

Data packet

 $\label{lem:decourse} $$\#D\#date;time;lat1;lat2;lon1;lon2;speed;course;height;sats;hdop;inputs;outputs;adc;ibutton;params\r\n $$$

date	Date in UTC format, DDMMYY, if no data, NA is sent		
time	Time in UTC format, HHMMSS, if no data, NA is sent		
lat1;lat2	Latitude (5544.6025;N), if no data, NA;NA is sent		
lon1;lon2	Longitude (5544.6025;N), if no data, NA;NA is sent		
speed	Speed, integer, km/h, if no data, NA is sent		
course	Course, integer, degrees, if no data, NA is sent		
height	Height, , integer, m, if no data, NA is sent		
sats	Number of satellites, integer, if no data, NA is sent		
hdop	Horizontal Dilution of Precision, double, if no data, NA is sent		
inputs	Digital inputs, each bit corresponds to one digital input beginning from		
	the LSB, integer, if no data, NA is sent		
outputs	Digital outputs, each bit corresponds to one digital output beginning from		
	the LSB, integer, if no data, NA is sent		
adc	Analog inputs, fractional numbers separated by comma, if no data, empty		
	string is send. Input numbering begins from 1 (adc1adcN).		
	Example 14.77,0.02,3.6		
ibutton	Driver key code, custom length string. If no data, NA is sent		
params	Set of additional parameters separated by comma. Each parameter has the		
	following format: NAME:TYPE:VALUE		
	NAME – custom string		
	TYPE – parameter type, 1 – int/long long, 2 – double, 3 – string		
	VALUE – parameter value, depends on type		
	T111-4		
	To send panic button use parameter with 1 type named "SOS", 1 mean		
	panic button was pressed.		
	To send text message use parameter with 3 type named "text". This		
	parameter can be used to send driver message with position and other		
	parameters.		
	Example: count1:1:564,fuel:2:45.8,hw:3:V4.5		
	Example, count1.1.304,10c1.2.43.6,11w.3. V4.3		

If date and time fields is NA, server will set current time for packet.





Server sends AD packet as an answer to D packet:

```
"-1" – packet structure error
```

Example:

 $\#AD\#1\r\n$

 $\#AD\#0\r\n$

 $\#AD\#10\r\n$

 $\#AD\#11\r\n$

...

 $\#AD\#15\r\n$

Ping (heartbeat) packet

 $\#P\#\r\n$

This packet is used for keeping active TCP-connection to server and checking channel availability.

Server sends AP packet as an answer to P packet:

Example:

 $\#AP\#\r\n$

Blackbox packet

 $\#B\#msg\r\n$

Blackbox packet is used for transmission of several messages at one time. In this case "msg" contains several SD or D packets bodies (without type signature), separated by "| "symbol.



[&]quot;0" – incorrect time

[&]quot;1" - packet successfully registered

[&]quot;10" – error getting coordinates

[&]quot;11" – error getting height, speed or course

[&]quot;12" - error getting amount of satellites or HDOP

[&]quot;13" – error getting inputs or outputs

[&]quot;14" – error getting adc

[&]quot;15" – error getting additional parameters



Example:

#B#date;time;lat1;lat2;lon1;lon2;speed;course;height;sats|date;time;lat1;lat2;lon1;lon2;speed;course;height;sats|date;time;lat1;lat2;lon1;lon2;speed;course;height;sats\r\n

Server sends AB packet as an answer to B packet, where number of registered messages is specified:

Example: #AB#3\r\n #AB#0\r\n

Message to driver

 $#M#msg\r\n$

Serves for sending a text message to driver. "msg" is the actual text. Message can be sent from either server or tracker.

Server sends AM command as a reply to message from driver.

"1" – message received
"0" – error receiving message

Example: #AM#1\r\n #AM#0\r\n





Packet with photo

That type of packet is used for sending photos to Wialon's server. The whole photo is separated into blocks of bytes and then each of them is sent to the server. Recommended size of one single block is up to 50 kb. If server fails to receive any image block, it breaks the connection. In this case we recommend to reduce the size of blocks.

#I#sz;ind;count;date;time;name\r\nBIN

SZ	size of packet's binary data (i.e., 512 bytes)	
ind	index number of transmitting block (numbering starts from zero)	
count	index number of last transmitting block	
date	data in DDMMYY format, in UTC	
time	time in HHMMSS format, in UTC	
name	name of transmitting photo	
BIN	photo's binary block	

Server sends AI command as a reply to packet with photo: #AI#ind;0/1\r\n

"1" – packet with block of photo is received

"0" – error receiving packet

 $#AI#1\r\n - photo is completely received and saved in Wialon$

Example:

Tracker: #I#51200;0;1;070512;124010;sample.jpg\r\nBIN

Server: #AI#0;1\r\n

Server: #AI#1;1\r\n Server: #AI#1\r\n





Packet with new firmware

Serves for sending new firmware to tracker. #US#sz\r\nBIN

SZ	Size of firmware's binary data
BIN	Firmware in binary mode

Packet with configuration file

Serves for sending configuration file to tracker. #UC#sz\r\nBIN

SZ	Size of configuration file, bytes
BIN	Content of configuration file

Incoming data (UDP)

All data is sent and received in plain text format and have the same structure as in TCP protocol, but with adding of IMEI in the beginning of packet. For example, short data packet will look in the following way:

imei#SD#date;time;lat1;lat2;lon1;lon2;speed;course;height;sats\r\n





Data compression

All Willon IPS data packets directed to server can be compressed before sending. It's useful for transferring large #B# packets.

For compression should be used the DEFLATE algorithm from **zlib** library (http://www.zlib.net/, RFC 1951).

Both of transport protocols are supported (TCP and UDP). Server always sends usual data packets (without compression) because its answers are small.

Structure of the container with compressed package:

Size	1 byte	2 bytes	Specified size
Content	Compression sign –	Size of compressed	Compressed data
	0xFF byte	data (little-endian, 16-	block, specified size,
		bit integer)	as-is

Container should contain only one packet of text protocol.

When compression is used, there is no necessary to append chars $\r\n$ to end of text protocol packet so they can be omitted before compression.

Compression is transparent for server that's why it can receive compressed and usual packets from one tracker at the same time.

Example of compressed packet:

Source packet	#L#imei;password	
Full data of	FF1800 <mark>78DA53F651CECC4DCDB42E482C2E2ECF2F4A01002D1C05E</mark>	
compressed		
packet	FF – compression sign	
(27 bytes, in	1800 – size of compressed data, means 24 (0x18) bytes	
HEX)	78DA compressed data	

